



Installing Arbortext® Editor™, Styler™, and Architect™

Arbortext 6.0 F000

February 2011

Copyright © 2011 Parametric Technology Corporation and/or Its Subsidiary Companies. All Rights Reserved.

User and training guides and related documentation from Parametric Technology Corporation and its subsidiary companies (collectively "PTC") are subject to the copyright laws of the United States and other countries and are provided under a license agreement that restricts copying, disclosure, and use of such documentation. PTC hereby grants to the licensed software user the right to make copies in printed form of this documentation if provided on software media, but only for internal/personal use and in accordance with the license agreement under which the applicable software is licensed. Any copy made shall include the PTC copyright notice and any other proprietary notice provided by PTC. Training materials may not be copied without the express written consent of PTC. This documentation may not be disclosed, transferred, modified, or reduced to any form, including electronic media, or transmitted or made publicly available by any means without the prior written consent of PTC and no authorization is granted to make copies for such purposes.

Information described herein is furnished for general information only, is subject to change without notice, and should not be construed as a warranty or commitment by PTC. PTC assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

The software described in this document is provided under written license agreement, contains valuable trade secrets and proprietary information, and is protected by the copyright laws of the United States and other countries. It may not be copied or distributed in any form or medium, disclosed to third parties, or used in any manner not provided for in the software licenses agreement except with written prior approval from PTC.

UNAUTHORIZED USE OF SOFTWARE OR ITS DOCUMENTATION CAN RESULT IN CIVIL DAMAGES AND CRIMINAL PROSECUTION. PTC regards software piracy as the crime it is, and we view offenders accordingly. We do not tolerate the piracy of PTC software products, and we pursue (both civilly and criminally) those who do so using all legal means available, including public and private surveillance resources. As part of these efforts, PTC uses data monitoring and scouring technologies to obtain and transmit data on users of illegal copies of our software. This data collection is not performed on users of legally licensed software from PTC and its authorized distributors. If you are using an illegal copy of our software and do not consent to the collection and transmission of such data (including to the United States), cease using the illegal version, and contact PTC to obtain a legally licensed copy.

Important Copyright, Trademark, Patent, and Licensing Information: See the About Box, or copyright notice, of your PTC software.

UNITED STATES GOVERNMENT RESTRICTED RIGHTS LEGEND

This document and the software described herein are Commercial Computer Documentation and Software, pursuant to FAR 12.212(a)-(b) (OCT'95) or DFARS 227.7202-1(a) and 227.7202-3(a) (JUN'95), and are provided to the US Government under a limited commercial license only. For procurements predating the above clauses, use, duplication, or disclosure by the Government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software Clause at DFARS 252.227-7013 (OCT'88) or Commercial Computer Software-Restricted Rights at FAR 52.227-19(c)(1)-(2) (JUN'87), as applicable. 01012011

Parametric Technology Corporation, 140 Kendrick Street, Needham, MA 02494 USA

Contents

About This Guide.....	5
Supported Systems and Requirements	9
Core Product Supported Systems	10
Supported Systems for Other Products and Options	12
Platform Specific Requirements	20
Setting Up Arbortext Editor to Use Arbortext Publishing Engine	21
Pre-Installation Upgrade Tasks	23
Pre-Installation Tasks Overview	24
After Upgrading from a Previous Version.....	24
Software Upgrade Preparation	25
Software Upgrade Considerations	26
Migrating Customizations	27
Post-Installation Upgrade Tasks.....	29
Post-Installation Task Overview.....	30
Using the Custom Directory	30
Setting the writeentdecls Command	30
Editing ACL Scripts	31
Package Customizations	31
Tag Template Customizations	31
Testing Your Customizations	32
Windows Installation Alternatives	33
Installation Alternatives.....	34
Installing on Microsoft Windows Vista and 7	34
Developing a Compact Installation	35
Performing a Windows Active Directory installation	36
Installation	39
Installation Overview	40
Standard Installation Procedure	41
Product Option Configuration on Windows	45
License Information	49
Licensing Options for Arbortext Software	50
Licensing Prerequisites	52
Obtaining Licenses	54
Requesting Licenses.....	54
Receiving Your License Pack.....	56
Installing and Updating the License Server.....	56
PTC_D_LICENSE_FILE Environment Variable	57

Borrowing a License.....	58
Troubleshooting Licensing Problems	59
Index.....	61



About This Guide

This guide contains installation and licensing information for Arbortext Editor, Arbortext Styler, Arbortext Architect, and the following product options:

- Arbortext Print Composer option
- Arbortext Web/Wireless Composer option
- Arbortext Import/Export
- PTC Server connection
- Arbortext Adapter to Documentum/XML
- Arbortext Adapter to Documentum/WDK
- Arbortext Adapter to Documentum
- Arbortext Adapter to Oracle CM SDK
- Arbortext Adapter to IBM Document Manager

Note

See the Arbortext Editor, Styler, and Architect Release Notes for updated information about the Arbortext product lines and product options.

Prerequisite Knowledge

This guide is intended for systems administrators. It is assumed that you are familiar with the operating system at your site and with standard system administration tasks.

Related Documentation

For more information refer to the Arbortext Editor Help Center.

Technical Support

Contact PTC Technical Support using the PTC Web site, phone, fax, or e-mail if you encounter problems using your product or the product documentation.

For complete information, refer to Contacting Technical Support in the PTC Customer Service Guide. This guide can be found on the PTC Web site at:

<http://www.ptc.com/support/>

The PTC Web site also provides a search facility for technical documentation of particular interest. To access this search facility, use the URL above and select Search the Knowledge Base.

You must have a Service Contract Number (SCN) before you can receive technical support. If you do not have an SCN, contact PTC Maintenance Department using the instructions found in your PTC Customer Service Guide under Contacting Your Maintenance Support Representative.

Documentation for PTC Products

You can access PTC product documentation using the following resources:

- Online Help

Click **Help** from the user interface for online help available for the product.

- Reference Documents

Individual product manuals are available from the Reference Documents link of the PTC Web site at the following URL:

<http://www.ptc.com/support/>

- Help Center

A searchable product documentation knowledge base is available from the Help Center link of the PTC Web site at the following URL:

<http://www.ptc.com/support/>

You must have a Service Contract Number (SCN) before you can access the Reference Documents or Help Center Web site. If you do not have an SCN, contact PTC Maintenance Department using the instructions found in your PTC Customer Service Guide under Contacting Your Maintenance Support Representative.

Global Services

PTC Global Services delivers the highest quality, most efficient and most comprehensive deployments of the PTC Product Development System including Pro/ENGINEER, Windchill, Arbortext and Mathcad. PTC's Implementation and Expansion solutions integrate the process consulting, technology implementation,

education and value management activities customers need to be successful. Customers are led through Solution Design, Solution Development and Solution Deployment phases with the continuous driving objective of maximizing value from their investment.

Contact your PTC sales representative for more information on Global Services.

Comments

PTC welcomes your suggestions and comments on our documentation. You can submit your feedback to the following email address:

arbortext-documentation@ptc.com

Please include the following information in your email:

- Name
- Company
- Product
- Product Release
- Document or Online Help Topic Title
- Level of Expertise in the Product (Beginning, Intermediate, Advanced)
- Comments (including page numbers where applicable)

Documentation Conventions

This guide uses the following notational conventions:

- **Bold text** represents exact text that appears in the program's user interface. This includes items such as button text, menu selections, and dialog box elements. For example,
Click **OK** to begin the operation.
- A right arrow represents successive menu selections. For example,
Choose **File ► Print** to print the document.
- Monospaced text represents code, command names, file paths, or other text that you would type exactly as described. For example,
At the command line, type `version` to display version information.
- *Italicized monospaced text* represents variable text that you would type. For example,
`installation-dir\custom\scripts\`
- Italicized text represents a reference to other published material. For example,

If you are new to the product, refer to the Getting Started Guide for basic interface information.

1

Supported Systems and Requirements

Core Product Supported Systems	10
Supported Systems for Other Products and Options	12
Platform Specific Requirements	20
Setting Up Arbortext Editor to Use Arbortext Publishing Engine	21

This chapter provides information on the supported platforms and requirements for Arbortext Editor, Arbortext Styler, Arbortext Architect, and other product options. It also contains system requirements for supported platforms.

Core Product Supported Systems

This section provides information on supported platforms and requirements for the basic Arbortext Editor product suite.

Support for Arbortext Editor

The following table lists the supported platforms and versions for Arbortext Editor 6.0.

Arbortext Editor Supported Systems

Windows				
XP	Vista	7	Server 2003	Server 2008
X	X	X	X	X
X — indicates certification If you're performing a Windows installation to share with Windows client installations, install to one of the Windows servers. Both the 32 and 64-bit versions of Windows are supported.				

The CJK language locales (Chinese, Japanese, or Korean) are automatically enabled for the appropriate corresponding system locale in Arbortext Editor.

Browser Support for Web Preview and Output

The web browser support applies to the Publish HTML File feature and the Publish For Web output.

Web Browser Support

Browser and version		Windows			Solaris	
		XP	Vista	7	9	10
Microsoft Internet Explorer	8.0	X	X	X	NA	NA
	7.0	X	X	X	NA	NA
Mozilla Firefox	3.6*	X	X	X	X	X
X — indicates certification NA — not available *All previous 3.x versions are also supported						

Internet Protocol Version 6 Support

Arbortext Editor supports Internet Protocol Version 6 (IPv6).

Sun's JVM Delivered with Arbortext Editor

The JVM delivered for this release is contained in the Java Runtime Environment. Several product features rely on the embedded JVM:

- All publishing features that use XSL stylesheets
- Java AOM/DOM interface, including the **Java Console** (available from the **Tools** menu, or you can use the `java_console` function)
- JavaScript

To see the current Java VM Version included with Arbortext Editor, select **Tools** ► **Administrative Tools** ► **Java Console** to open the **Arbortext Java Console**.

Perl Version for APP Delivered with Arbortext Styler or Arbortext Publishing Engine

An Arbortext installation that includes Arbortext Styler or Arbortext Publishing Engine also includes a packaged installation of the APP print engine and associated support files, plus the Perl release needed to support the APP print engine functionality. This installation does not require additional licensing. The installed Perl DLL `perl58.dll`, installed to the directory `Arbortext-path/app/perl/bin`, provides Perl release 5.8, which is necessary to support this installation.

You may prefer to specify the location of an alternative Perl installation to that supplied with your Arbortext environment. Please use the environment variable `APTAPPPERL` to define the path to the root folder of the desired Perl installation. Note that this directory must contain a `\bin` subdirectory containing the Perl version 5.8 DLL `perl58.dll`.

Note that an installation of Arbortext without Arbortext Styler or Arbortext Publishing Engine does not include APP.

Arbortext Help Center Requirements

The Arbortext Help Center runs using an embedded browser based on Internet Explorer. Changes you make to the settings in Internet Explorer, such as text size, might affect the Help Center as well.

Requirements for Hosting ActiveX Controls

When running on Windows XP, Vista, or 7, Arbortext Editor can host ActiveX controls through an underlying Active Script engine. To establish Arbortext Editor as an Active Script host, you must have the system files `jscript.dll`, `vbscript.dll` and `scrrun.dll`. These files are typically found in your system folder, and are likely already installed on your system if you have installed Internet Explorer 4.0 or higher.

Additionally, to ensure you have the latest updates and capabilities, it is recommended that you download and install the most recent version of the Microsoft Windows Script Host. (The current version is 5.8.)

You may also want to download the following applications:

- Microsoft Script Component Wizard — to create Windows Script Components
- Microsoft Script Debugger — to employ an interactive script debugger

You can download these applications from Microsoft's MSDN:

msdn.microsoft.com

Requirements for Running Arbortext Editor's ActiveX Sample Applications

You must have the Microsoft Calendar Control installed to properly run the Calendar sample script. This control is usually installed when you install Microsoft Access. If you do not have the file `MSCAL.OCX` installed on your system, you can download the file from the following URL:

www.fontstuff.com/mailbag/qvba01.htm

You must have the Microsoft WebBrowser control installed to enter address information as part of the HTML form sample. This control resides in `SHDOCW.DLL`, and is installed as part of Internet Explorer 4.0 or higher.

Supported Systems for Other Products and Options

This section provides information on supported platforms and requirements for other Arbortext products and product options.

Arbortext Styler

Arbortext Styler is supported on the following systems:

Arbortext Styler Supported Systems

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

Arbortext Architect

Arbortext Architect is supported on the following systems:

Arbortext Architect Supported Systems

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

Turbo XML for Arbortext Architect

Arbortext Architect can use Turbo XML, a graphical user interface product from Extensibility, Inc., for editing XML DTDs and schemas. Turbo XML can be installed separately following your installation of Arbortext Editor.

Note

*The Turbo XML product is no longer supported by TIBCO Software, Inc. and is not officially supported on Microsoft Windows XP, Vista, or 7. Turbo XML should run on Microsoft Windows XP for users that log on with administrator privileges. On Windows Vista and 7, you must run Turbo XML in Windows XP compatibility mode. To set the compatibility mode, view the properties of the Turbo.exe executable file, select the **Compatibility** tab on the properties dialog box, and select Windows XP for the **Compatibility mode** setting.*

Turbo XML will continue to be delivered with Arbortext Architect. However, no Turbo XML issues will be addressed by either TIBCO or PTC.

Arbortext Print Composer Option

The Arbortext Print Composer option is available on the following systems:

Arbortext Print Composer Option Supported Systems

Windows				
XP	Vista	7	Server 2003	Server 2008
X	X	X	X	X
X — indicates certification				

If this installation of Arbortext Editor will be using Arbortext Publishing Engine to perform document publishing, Arbortext Print Composer and/or the Arbortext Web/Wireless Composer product options will also be installed on the Arbortext Editor client to make the publishing menu choices available. Also, the version of Arbortext Editor on each workstation must be 5.3 M040 or later to support Arbortext Publishing Engine 6.0 F000 on the server.

If you will be using the Arbortext Print Composer option with Adobe Acrobat Distiller Server to produce PDF or PostScript output, you should set the display resolution to at least 65K or 16-bit color.

Arbortext Web/Wireless Composer Option

The Arbortext Web/Wireless Composer option is available on all Arbortext Editor supported platforms and systems. Refer to the table in *Browser support for web preview and output* for supported browser versions.

If this installation of Arbortext Editor will be using Arbortext Publishing Engine to perform document publishing, Arbortext Print Composer and/or the Arbortext Web/Wireless Composer product options will also be installed on the Arbortext Editor client to make the publishing menu choices available.

Publishing documents for DMP is available with the Web/Wireless license. Publishing files for use with DMP does not require that Digital Media Publisher be installed on your workstation. However, if DMP is not installed on your workstation and you are not publishing using the Arbortext Publishing Engine, you will only be able to create files that can be used as input to a DMP image created at a later time (with DMP). Digital Media Publisher is included with the Arbortext Publishing Engine.

Arbortext Import/Export

Arbortext Import/Export is available on all Arbortext Editor supported platforms and systems. Arbortext Import/Export requires the Arbortext Publishing Engine to import and export documents.

Arbortext Import/Export Supported Systems

Windows		
XP	Vista	7
X	X	X
X — indicates certification		

- Arbortext Import/Export must be installed and licensed on your Arbortext Publishing Engine.

Export stylesheet development, Import MapTemplate development, and document conversion can be performed directly on an Arbortext Publishing Engine server using Arbortext PE Interactive. The Arbortext Publishing Engine is also the engine used by client workstations performing document conversions.

- To import and export files (and do no Import MapTemplate or Export Stylesheet development), each Arbortext Editor workstation must be configured to use the Arbortext Publishing Engine for publishing.

Ensure that each client workstation has `featureImportExport` set to `on` in their `installprefs.acl` file and has the following set option values (or Advanced Preference settings):

- `peservices = on`
- `peserverurl = <your_PE_server_name>`

If your workstation is not currently connected to an Arbortext Publishing Engine server licensed for Arbortext Import/Export, you will not be able to import or export documents using Arbortext Import/Export.

- To develop export stylesheets on Arbortext Editor client workstations, Arbortext Styler and Arbortext Import/Export must be licensed and installed on these workstations. Ensure these workstations have the same `installprefs.acl` and Advanced Preference settings as those for workstations used to import and export files.
- To develop Import MapTemplates, Microsoft .NET Framework Version 2.0 Redistributable Package (x86) and .NET Compact Framework 2.0 Service Pack 1 Redistributable (or .NET Version 3.0 which includes the .NET Version 2.0 Framework) must be installed on each Arbortext Editor client workstation where Arbortext Import/Export will be used.

Arbortext Import/Export must also be installed and licensed on these workstations. Ensure these workstations have the same `installprefs.acl` and Advanced Preference settings as those for workstations used to import and

export files. Additionally, ensure that `featureImportMapping` is set to on in each workstation's `installprefs.acl` file.

- Arbortext Import does not support importing Hebrew, Arabic, and Thai content.

Refer to the Arbortext Import/Export chapter of the Arbortext Customizer's Guide for information on configuring and using Arbortext Import/Export.

Dynamic Link Manager

Dynamic Link Manager clients are available on all Arbortext Editor supported platforms and systems. Workstations must be running the same release of Dynamic Link Manager as the Dynamic Link Manager server.

Refer to the Dynamic Link Manager chapter in the Arbortext Customizer's Guide for complete Dynamic Link Manager platform requirements.

PTC Server connection

The PTC Server connection is available on the following systems for connecting to the Arbortext Content Manager:

PTC Server connection Supported Systems for the Arbortext Content Manager

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

The PTC Server connection is available on the following systems for connecting to Windchill PDMLink:

PTC Server connection Supported Systems for Windchill PDMLink

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

The PTC Server connection is available on the following systems for connecting to Windchill ProjectLink:

PTC Server connection Supported Systems for Windchill ProjectLink

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

The PTC Server connection is supported for the following PTC content management systems:

- Arbortext Content Manager 9.1 M060 or later
- Windchill PDMLink 9.1 M060 or later
- Windchill ProjectLink 9.1 M060 or later

Internet Protocol Version 6 Support

The PTC Server connection supports Internet Protocol Version 6 (IPv6).

Arbortext Adapter to Documentum/XML

The Arbortext Adapter to Documentum/XML is available on the following systems:

Arbortext Adapter to Documentum/XML Supported Systems

Windows
XP
X
X — indicates certification

The following table provides the repository requirements for the Arbortext Adapter to Documentum/XML:

Arbortext Adapter to Documentum/XML Requirements

Documentum Content Server	Documentum Desktop Client
6.0 or 6.5	5.3

Note

The Arbortext Adapter to Documentum/XML does not support Documentum Desktop Client 5.3 SP5.5.

Arbortext Adapter to Documentum/WDK

The Arbortext Adapter to Documentum/WDK is available on the following systems:

Arbortext Adapter to Documentum/WDK Supported Systems

Windows		
XP	Vista	7
X	X	X
X — indicates certification Both the 32 and 64-bit versions of Windows are supported.		

The following table provides the repository requirements for the Arbortext Adapter to Documentum/WDK:

Arbortext Adapter to Documentum/WDK Requirements

Documentum Content Server	Documentum Webtop
6.0 or higher	6.0 or 6.5 running on the Apache/Tomcat Application Server or the Oracle WebLogic Application Server

We are not aware of any issues with using Federated or Replicated docbases with the Arbortext Adapter to Documentum/WDK. However, the adapter has not been certified with Federated or Replicated docbases.

Web Browser Support

The Arbortext Adapter to Documentum/WDK is supported on Microsoft Internet Explorer 7.0 and 8.0.

Internet Protocol Version 6 Support

The Arbortext Adapter to Documentum/WDK supports Internet Protocol Version 6 (IPv6). Note that IPv6 support requires Documentum Webtop version 6.5 or later.

Arbortext Adapter to Documentum

The Arbortext Adapter to Documentum is available on the following systems:

Arbortext Adapter to Documentum Supported Systems

Windows
XP
X
X — indicates certification

The following table provides the repository requirements for the Arbortext Adapter to Documentum:

Documentum Requirements

Documentum Content Server	Documentum Desktop Client
6.0 or higher	5.3

Arbortext Adapter to Oracle CM SDK

The Arbortext Adapter to Oracle CM SDK servlet is installed on the Oracle host, and is supported on Windows, Solaris, and Linux systems only.

Arbortext Adapter to Oracle CM SDK Client Supported Systems

Windows		
XP	Vista	7
X	X	X
X — indicates certification		
Both the 32 and 64-bit versions of Windows are supported.		

The Arbortext Adapter to Oracle CM SDK is supported for the following Oracle systems:

- CM SDK 10g (9.0.4)
- CM SDK 10.2 (9.0.4.2)

Arbortext Adapter to IBM Document Manager

The Arbortext Adapter to IBM Document Manager is available on the following systems:

Arbortext Adapter to IBM Document Manager Supported Systems

Windows	
XP	Vista
X	X
X — indicates certification	

The following IBM DB2® Document Manager requirements must be met to install and use this adapter successfully:

- The repository must be installed and configured on the server.
- IBM DB2 Content Manager must be at an 8.3 Fix Pack 6 or later.
- IBM DB2 Document Manager must be at an 8.3 Fix Pack 6 or later.

Platform Specific Requirements

The following sections provides hardware, system, and other requirement information.

Windows System Requirements

Any Windows system running Arbortext software must meet the following list of hardware and software requirements.

Hardware Requirements

If your system can run the associated operating system effectively, then that system should be able to run your Arbortext software without an issue. Disk space requirements are approximately 930 MB to 1.1 GB, depending on the product options included in the installation. The Arbortext installation program displays the space required for the base program and each of the product options.

Screen Fonts

Arbortext software works best when used with TrueType (TT) or PostScript Type 1 (PS1) fonts. Raster fonts may cause display problems.

Other Windows Software Requirements

- The **File ► Publish ► For HTML Help** feature requires the Microsoft HTML Help Workshop. The Workshop is a free download from:

msdn.microsoft.com/en-us/library/ms669985.aspx

When you install the HTML Help Workshop, you must start and close the **HTML Help Workshop** application once before you use the **File ► Publish ► For HTML Help** menu option.

- Arbortext Editor is compatible with [JAWS accessibility screen reader software](#) version 5.0 or later. For more information, refer to *Arbortext-path* \samples\jaws\Readme.txt.

Note that the JAWS accessibility screen reader does not run on 64-bit versions of Windows.

Setting Up Arbortext Editor to Use Arbortext Publishing Engine

You can perform all publishing tasks using Arbortext Publishing Engine in the same manner you would locally. If your installation of Arbortext Editor will be using Arbortext Publishing Engine for publishing documents, you will need to enter some information to connect to it.

The Arbortext Editor installation procedure prompts you for the location of Arbortext Publishing Engine. If you didn't have that information at the time of installation, you will need to set it up in **Tools ► Preferences ► Publishing Engine**.

1. Check the box for **Use Publishing Engine**.
2. You will need to obtain the URL for your site's Arbortext PE server from your Arbortext PE administrator. Enter the **URL** following the form:

`http://server-name:port-number/e3/servlet/e3`

where *server-name* is the host name of the server and *port-number* is the port that requests should be sent through.

3. Click the **Apply** button to test the URL to assure it is correct.

The **Status** field reports whether the URL successfully connects to an Arbortext PE server.

If the connection fails, click the **Show Connection Error** button to display the error message from the Arbortext PE server. If you re-enter your URL and it fails again, contact your Arbortext PE administrator and report the error.

Note

One reason the connection may fail is if Arbortext Editor is running on a different type of network than Arbortext PE. Both Arbortext Editor and Arbortext Publishing Engine support IPv4 and IPv6, but they must both be running on the same type of network to avoid an error. Check with your system administrator to resolve networking issues.

Be sure to read [Using Arbortext Publishing Engine for publishing documents](#) in the Arbortext Help Center for extensive information about publishing in this manner.

Local publishing requires that Arbortext Styler, Arbortext Print Composer and/or the Arbortext Web/Wireless Composer product options are installed on the Arbortext Editor client to make the publishing menu choices available.

If you need more information about setting up Arbortext Publishing Engine, consult the Arbortext Publishing Engine documentation or your Arbortext Publishing Engine administrator.

2

Pre-Installation Upgrade Tasks

Pre-Installation Tasks Overview	24
After Upgrading from a Previous Version	24

This chapter contains tasks you should perform before upgrading Arbortext Editor.

Pre-Installation Tasks Overview

The following tasks should be performed before you install the new version of Arbortext Editor.

- Obtain a new license for your upgraded version. Refer to [Obtaining Licenses on page 54](#) for more information.

After Upgrading from a Previous Version

After you have installed Arbortext Editor successfully, and migrated your customizations, [Post-installation upgrade tasks on page 29](#) provides detailed instructions for tasks that must be performed in order for Arbortext Editor to operate properly.

3

Software Upgrade Preparation

Software Upgrade Considerations.....	26
Migrating Customizations	27

This chapter contains information about things you might want to do before upgrading from a previous version of Arbortext Editor.

Software Upgrade Considerations

This section contains information that is helpful when you are upgrading from a previous version of Arbortext Editor. Review it before proceeding with the installation of your software, particularly if you have any customizations that need to be migrated to the new version.

Upgrading from a Previous Version

The 6.0 version of Arbortext Editor is a full installation.

- If you are currently running the 5.4 or earlier version of Arbortext Editor, then the 6.0 version is a new release and cannot upgrade the 5.4 or earlier version. If you no longer want to have the 5.4 or earlier version on your system, you must uninstall that version.
- If you will be temporarily running both the 6.0 version of Arbortext Editor and the 5.4 or earlier version, install the new version in a different directory from your current version.
- You may have customized files from previous installations located in different directories. If you want to maintain custom files, you need to save them in a temporary location for evaluation after you upgrade. For example, you may have files with specific configuration settings that you will want to use to update the new configuration files. Be sure to copy your custom files to a temporary location so they will be available after you upgrade.

If your current Arbortext Editor installation does not include customizations that need to be migrated to the new version, you can proceed to the installation and licensing section that is appropriate to your site. After you have successfully installed the new version, you will need to perform the post-installation upgrade tasks described in [Post-installation upgrade tasks on page 29](#).

Upgrading on Windows

On Windows, you cannot upgrade from a 5.4 or earlier version to the 6.0 version. You must do a full installation.

Note

Generally, upgrades can be performed on F000 and subsequent M0n0 releases. However, in rare cases it's possible that a M0nx version might be released after the next M0n0 version. Because releases are cumulative, this upgrade situation would require installing the next M0n0 version rather than an upgrade. For instance, if an M020 version is released in April, followed by an M015 release in May, an upgrade from M015 to M020 would not be possible as it was released after M020. The next upgrade path would become M030 or later.

If you choose to uninstall a previous version and then reuse the installation path for your upgrade and its directories are not empty, you'll be advised to install to another location.

Migrating Customizations

If your current installation has been customized using environment variables or custom scripts or applications, you will need to migrate these customizations to this version of Arbortext Editor. It is recommended that you first install Arbortext Editor on a test system reflecting your current user environment. It should not have been previously customized or have the customizations disabled.

If you are upgrading from Arbortext Publishing Engine 4.3 or higher, you may have placed custom files in the `PE_HOME\custom` subdirectory structure. The uninstall feature leaves your custom files in the `custom` directory intact. You can reuse the previous install path if you have files in the `custom` directory. The upgrade installation only overwrites an existing file having the same name and path. If you placed custom files in other install tree locations, the upgrade could overwrite them. If you prefer a clean installation, you can copy the entire directory and its contents to a backup location. After you complete the upgraded installation, you can migrate your custom files to the upgraded installation `custom` directory.

Perform the following procedure on your test system to ensure that all customizations have been removed or disabled:

1. Check your environment variables for any that relate to Arbortext Editor.
In general, you should check all environment variables you have set up for your Arbortext Editor environment to make sure they are all relevant and current. For instance, you could have `APTCUSTOM` set to a path list that has changed due to upgrading to your installation.
2. Record the current settings of any Arbortext Editor environment variables, so that you can reset them appropriately after you have installed the new version.
3. Delete all Arbortext Editor environment variables.

Caution

Once you've set the `PTC_D_LICENSE_FILE` environment variable, don't delete it. This provides access to your licenses. However, the licenses themselves need to be upgraded. You may need to verify that the upgraded license file or license server location has not changed.

4. Disable any scripts, applications, or files that may be part of the current version's customizations.

You can now install Arbortext Editor on your test system according to the procedures in the installation and licensing chapters.

After you have successfully installed the new version, you will need to perform the post-installation upgrade tasks described in [Post-installation upgrade tasks on page 29](#).

4

Post-Installation Upgrade Tasks

Post-Installation Task Overview	30
Using the Custom Directory	30
Setting the writeentdecls Command	30
Editing ACL Scripts	31
Package Customizations	31
Tag Template Customizations	31
Testing Your Customizations.....	32

This chapter contains tasks you should perform after upgrading Arbortext Editor.

Post-Installation Task Overview

The following tasks should be performed after you have successfully installed the new version of Arbortext Editor.

- Copy your customized files to the new `custom` subdirectory structure on the test system.
Refer to [Using the custom directory on page 30](#) for more information.
- Set the `wroteentdecls` command, if necessary.
Refer to [Setting the wroteentdecls command on page 30](#) for more information.
- Edit your ACL scripts, if necessary.
Refer to [Editing ACL scripts on page 31](#) for more information.
- Migrate your package customizations.
Refer to [Package customizations on page 31](#) for more information.
- Migrate your tag template customizations.
Refer to [Tag template customizations on page 31](#) for more information.
- Once you have successfully implemented and tested the recommended and optional customizations, move the new Arbortext Editor installation and its customizations to your production environment.

Using the Custom Directory

Arbortext Editor provides a `custom` directory structure within the Arbortext installation tree where you can store your custom applications. When Arbortext Editor starts, it automatically looks for files in this directory structure and loads them. You can place custom files such as Java (`.class` and `.jar`), JavaScript (`.js`), JScript (`.js`), VBScript (`.vbs`), ACL (`.acl`), and various configuration files in their supported locations within the `Arbortext-path\custom` subdirectory structure to make them available.

Refer to the Arbortext Programmer's Reference for more information.

Setting the wroteentdecls Command

Arbortext Editor includes the `set wroteentdecls` command, which controls how entity declarations are written in the subsets of the main document and in file entities. By default, entity declarations are written in the root document's subset, and only declarations referenced immediately within a child will be written to that child's subset.

If you wish to change the default setting, we recommend you set the option to be used site wide, and that you convert all documents and document objects to the new default by opening and saving them in Arbortext Editor.

Note

Refer to the [set writeentdecls online help topic](#) for more information.

Editing ACL Scripts

Changes to the new version of Arbortext Editor may require you to change your ACL scripts. Check your ACL scripts (`.acl`) to see if they are affected by the new or changed ACL commands and functions. The new and changed ACL commands and functions are listed in the Arbortext Editor, Styler, and Architect Release Notes .

Package Customizations

Your previous Arbortext Editor installations might have customizations of files in the `Arbortext-path\packages` directory. Many of the files in the `packages` subdirectory change from version to version, so you should compare the contents of your customized files to the new files.

You might want to add your customized `.acl` and `.js` files to the `Arbortext-path\custom\scripts` subdirectory.

Note

Customizations specific to a document type should be moved to document type command files (`doctype.js` or `doctype.acl`) or document type instance command files (`instance.js` or `instance.acl`) within the `custom\doctypes\doctype` directory.

Refer to [Using the Custom Directory on page 30](#) for more information.

Tag Template Customizations

If you had custom tag template files in your previous Arbortext Editor installations, you may want to add a `tagtemplates` subdirectory to the `Arbortext-path\custom` directory structure, and copy your customized files directly to that location.

Note

Arbortext Editor will not automatically process tag template customizations. Instead, you must specify the path to this file using the `APTTAGTPLDIR` environment variable. Do not append the `%D` symbol to this environment variable.

Refer to [Using the Custom Directory on page 30](#) for more information.

Testing Your Customizations

After incrementally migrating your customizations to this version of Arbortext Editor, thoroughly test the functionality. This is especially important in the areas of custom document types, profiling, and publishing for HTML and web.

Once you have successfully tested your customizations, move your Arbortext Editor installation to your production environment.

5

Windows Installation Alternatives

Installation Alternatives	34
Installing on Microsoft Windows Vista and 7	34
Developing a Compact Installation	35
Performing a Windows Active Directory installation.....	36

This chapter contains information on alternative ways to install Arbortext Editor.

Installation Alternatives

Depending on your site's specific needs, you might want to perform one or more of the operations listed in this chapter. These operations can facilitate the installation process. You might want to:

- Share the entire distribution archive from a Windows network. Users can then install the software from their remote Windows systems.
- Perform a Windows Active Directory installation for systems on a Windows network.
- Develop a compact installation for Arbortext Editor for users to download.
- If necessary, install or update the FlexNet license server. Sites that have floating licenses should install the license server before setting up individual users.

If none of these alternatives apply to your site, skip to [Standard Installation Procedure on page 41](#).

Installing on Microsoft Windows Vista and 7

The security features of Microsoft Windows Vista and Windows 7 can affect the Arbortext Editor install, uninstall, or licensing processes. Please be aware of the following issues when using Microsoft Windows Vista and Windows 7:

- When you install Arbortext Editor on Microsoft Windows Vista and Windows 7, a **User Account Control** dialog box appears asking whether you want the installation to proceed. Select **Allow** to proceed with the install process. The dialog box is displayed even when you are logged on with administrator privileges.
- When using the `msiexec` to install or uninstall Arbortext Editor, you must use an elevated command prompt.
- When you uninstall Arbortext Editor from the Microsoft Windows Vista and Windows 7 **Control Panel**, a **User Account Control** dialog box appears stating that **An unidentified program wants access to your computer**. Select **Allow** to proceed with the uninstall process.

Developing a Compact Installation

Besides the full installation of Arbortext Editor, you can also develop a compact installation that users can download from a web site or network share. A compact installation enables you to have a centralized location for any Arbortext Editor configuration or customizations required for your site.

The compact installation of Arbortext Editor is much smaller than the full installation and has somewhat less functionality. It is more appropriate for authoring, than developing customizations, custom document types, and so forth. The compact installation has the following significant differences in functionality from the full installation:

- Publishing requires Arbortext Publishing Engine.
- **File ► Print Preview** produces a PDF file and requires Adobe Reader.
- **File ► Print** also produces a PDF file and requires Adobe Reader.

The PDF file must be printed from Adobe Reader.

- The Arbortext Help Center might not be available.

The Help Center is an optional addition to the compact installation. If the Help Center is not available, the compact installation contains an HTML Help file with the Arbortext Editor and Arbortext Styler online help.

Developing a compact installation of Arbortext Editor requires several steps. First, you must determine the optional features you want to include in the installation and develop a Deploy Directory to hold the installation files associated with both those and the required features. The Deploy Directory must be hosted on a web server or network share that your users can access. Next, you must create a custom installer tied to the Deploy Directory to distribute to users. This installer is much simpler than the regular Arbortext Editor and presents fewer choices to the users. It is up to administrators to develop a compact installation that contains the correct feature set for their users. Finally, you must make the Deploy Directory and custom installer available to users. Note that a user must have administrator privileges on their system to install the compact installation.

An Arbortext Editor Deployment Kit is available to assist you with the development of a compact installation. For more information, refer to the Arbortext Editor Deployment Kit Guide.

Performing a Windows Active Directory installation

You can use the Windows Active Directory to install the distribution on multiple systems. You can base the installation on either the computers or users on your network. Refer to the Microsoft Windows Active Directory documentation for more information about performing an Active Directory installation.

Before performing the Active Directory installation, you can use an MSI file editor, such as the Windows Orca editor, to modify the properties in the Windows installation file (`Arbortext.msi`) to match the requirements of your environment. Refer to the following web site for more information about the Orca editor:

msdn2.microsoft.com/en-us/library/aa370557.aspx

Following are the properties (from the **Property** table) you can modify in the installation file, grouped by the installation dialog box on which they appear. Beside of each property in parenthesis is the default value for the property in the installation file. For properties that are either on or off, set the property to any value that does not start with the letter N or n to turn the property on. To turn a property off, there are two options. If the default is off, do not set the property at all. If the default is on, set the property to a value that starts with the letter N or n (for example, nO) to turn the property off. Note that properties that are off by default may not appear in the default **Property** table.

- **Products** dialog box
 - INSTALL_EDITOR (on)
 - INSTALL_STYLER (off)
 - INSTALL_ARCHITECT (off)
 - INSTALL_DESKTOP_ICONS (on)
- **File Types** dialog box
 - ASSOC_ACL (on)
 - ASSOC_SGM (on)
 - ASSOC_XML (on)
 - ASSOC_DCF (on)
 - ASSOC_MCF (on)
 - ASSOC_FOS (on)
 - ASSOC_STYLE (on)
 - ASSOC_DITA (on)

-
- **Help Center Languages dialog box**
 - `INSTALL_HELPCENTER_EN` (on) — English
 - `INSTALL_HELPCENTER_FR` (off) — French
 - `INSTALL_HELPCENTER_DE` (off) — German
 - `INSTALL_HELPCENTER_IT` (off) — Italian
 - `INSTALL_HELPCENTER_ES` (off) — Spanish
 - `INSTALL_HELPCENTER_JPN` (off) — Japanese
 - `INSTALL_HELPCENTER_KOR` (off) — Korean
 - `INSTALL_HELPCENTER_CHS` (off) — Simplified Chinese
 - `INSTALL_HELPCENTER_CHT` (off) — Traditional Chinese

Note that if the operating system locale is not English, the translated documentation corresponding to that locale will also be set to on.

- **Destination Folder dialog box**
 - `INSTALLDIR` (`C:\Program Files\Arbortext\Editor`)
- **Products dialog box**
 - `SETUP_TYPE` (Typical)

The allowed values for this property are `Typical`, `Complete`, and `Custom`. If you set this property to `Complete`, all of the optional product features will be installed. If you set this property to `Custom`, you can set the following additional properties for optional product features:

- `INSTALL_SMA_APPLICATION` (on)
- `INSTALL_DLM` (off)
- `INSTALL_IMPORT_EXPORT` (off)
- `INSTALL_IMPORT_WORKBENCH` (on when Arbortext Architect is included in the installation, off otherwise)
- `INSTALL_PRINT_COMPOSER` (on when Arbortext Styler is included in the installation, off otherwise)
- `INSTALL_PTC_SERVER_CONNECTION` (on)
- `INSTALL_WEB_WIRELESS_COMPOSER` (on when Arbortext Styler is included in the installation, off otherwise)
- `INSTALL_DOCUMENTUM` (off)
- `INSTALL_DOCUMENTUM_WDK` (off)
- `INSTALL_DOCUMENTUM_XML` (off)
- `INSTALL_IBMDM` (off)

-
- `INSTALL_ORACLE_CM_SDK` (off)
 - **Using Arbortext Publishing Engine dialog box**
 - `USING_PE` (off)

If you set the value of this property to on, then you must enter the URL for your Arbortext Publishing Engine server in the `PE_SERVER_URL` property or the Arbortext Publishing Engine will be unable to publish your documents.
 - `PE_SERVER_URL` (null)

6

Installation

Installation Overview.....	40
Standard Installation Procedure.....	41
Product Option Configuration on Windows.....	45

This chapter provides the standard installation procedures for Windows systems. This version is a full installation; no previous version of Arbortext Editor is required.

If you are replacing or upgrading from a previous installation, you should refer to [Software Upgrade Considerations on page 26](#).

You will need to obtain updated licenses for this release. You can enter licensing information the first time you run Arbortext Editor. Your system administrator may deploy some licensing information telling you how to enter the licensing information. Refer to [Obtaining Licenses on page 54](#) for information.

Installation Overview

To install your Arbortext software, you will need:

- The distribution DVD or the archive file you downloaded from the PTC support site.

First, determine if you want the 32 or 64-bit versions of the software. If you are downloading an archive file from the PTC support site, you have to choose which version of the archive file you want to download. If you are installing from the distribution DVD, the installation program asks you which version of the software you want to install.

- A list of the product options that your site has purchased.
- If you are installing the Arbortext Adapter to Documentum, you will need to know the location of your Documentum client software installation.

The Documentum client software must be installed and working correctly before you install the adapter. Each user will need access (using the system path or Documentum-specific environment variable) to the Documentum client software initialization file `dmcl.ini`.

- If you are installing the Arbortext Adapter to Documentum/XML, the Documentum client software must be installed and working correctly before you install the adapter.

To install your Arbortext software perform the following steps:

1. Make any necessary preparations before installation, such as making the installation files available on a server. See [Installation alternatives on page 34](#) for more information.
2. Install the software and product options.

Note

You must have administrator privileges to install Arbortext software on Windows systems.

3. Customize your licensing parameters if necessary.
4. If you installed a repository adapter, perform the necessary procedures to connect the repository adapter to your document repository.
5. Check the PTC Customer Support web site at www.ptc.com/support/support.htm for software updates that may apply to your installation.

Standard Installation Procedure

To install the Arbortext Editor software:

1. Start the Arbortext Editor `setup` program. Use the startup instructions that match your specific situation.

- Installing from a release file downloaded from the support site:

Unzip the file containing the release to a temporary directory on your local system (for example, `C:\Temp`). Select **Run** from the **Start** menu, browse to the temporary directory where you unzipped the release and locate the `\windows\setup.exe` program.

The `setup` program first asks you to select the language for your installation.

Select a language from the drop down list and click **OK** to continue the installation.

- Installing from the distribution DVD:

Insert the DVD in the DVD drive. The `setup.exe` program will run automatically.

Note

If AutoRun is disabled, you can select Run from the Start menu, browse to the drive for your DVD, and run the `setup.exe` program.

When you are installing from the DVD, the `setup` program displays the following initial dialog boxes:

- a. The `setup` program asks you to select the language for your installation.

Select a language from the drop down list and click **OK** to continue the installation.

- b. The `setup` program asks you to select either the 32 or 64-bit version of the software.

Select the version of the software you want to install and click **Next** to continue the installation.

You also have the option to explore the contents of the DVD.

- Installing from a network server:

Select **Run** from the **Start** menu, browse to the network drive and locate the `\windows\setup.exe` program.

2. The `setup` program displays a **Welcome** dialog box.

Click **Next** to continue the installation.

-
3. The `setup` program prompts you to accept the license agreement.

The license agreement is presented in the language you choose for the installation. You have the option to view the license agreement in another language.

Click **Accept** to continue the installation.

4. The `setup` program prompts you for the products to install.

You can install one or more products at a time. If you select more than one product, they will all be installed in the same location. You can also indicate whether you would like to create desktop icons for the installed products.

Select the appropriate products and indicate whether you would like to create desktop icons for them, then click **Next** to continue the installation.

5. The `setup` program prompts you to choose whether to make an association for the following file types and your new Arbortext Editor installation:

- Arbortext Command Language File (acl)
- SGML Document (sgm)
- XML Document (xml)
- Doctype Configuration File (dcf)
- Arbortext Macro File (mcf)
- FOSI Stylesheet (fos)
- Styler Stylesheet (style)
- DITA Documents (dita, ditamap)

Select the appropriate file associations, then click **Next** to continue the installation.

6. The `setup` program prompts you to select the localized documentation you would like to include in the Arbortext Help Center.

Select any languages you would like to include, then click **Next** to continue the installation.

7. The `setup` program prompts you to specify an installation folder.

You can accept the default location or select **Change** to specify a different location. If you specify a nonexistent folder, the `setup` program will create it for you.

Specify the appropriate destination folder, then select **Next** to continue the installation.

8. The `setup` program prompts you to select one of the following setup types for your installation:

-
- **Typical** — For an Arbortext Editor installation, installs the **Service Manual Application** and **PTC Server connection** features. For an Arbortext Editor with Styler installation, also installs the **Print Composer** and **Web/Wireless Composer** options and a subset of the **Import/Export** feature. For an Arbortext Architect installation, also installs the **Import Workbench** feature.
 - **Complete** — All optional features will be installed.
 - **Custom** — Opens the **Custom Setup** dialog box, from which you can select the features you want to install.

The **Custom Setup** dialog box enables you to choose from the following product features:

- The **Dynamic Link Manager** feature is an optional feature that is available with Arbortext Publishing Engine. The Arbortext client software also requires installation of DLM components.
- The **Import/Export** feature installs the Arbortext Import/Export product option. This feature requires an additional license. Refer to the Arbortext Customizer's Guide for instructions on configuring and using Arbortext Import/Export.
- The **Import Workbench** feature is also part of the Arbortext Import/Export product option and requires an additional license. This feature requires the installation of the latest version of .NET.
- The **Print Composer** feature installs the Arbortext Print Composer product option. This product option prepares your documents for print publishing and requires an additional license. Note that the Print Composer option is required to support Arbortext Publishing Engine publishing.
- The **Service Manual Application** feature installs the Service Manual Application. The Service Manual Application provides a customized editing and publishing environment for authoring service manuals. The Service Manual Application is based on the DITA standard.
- The **Web/Wireless Composer** feature installs the Arbortext Web/Wireless Composer product option. This product option requires an additional license.
- The **PTC Server connection** feature installs the PTC Server connection. The PTC Server connection provides an interface between Arbortext Editor and either Arbortext Content Manager, Windchill PDMLink, or Windchill ProjectLink.
- The **Optional Adapters** feature can be customized. Click on the “+” next to **Optional Adapters** to open the list of optional repository adapters. Select the optional adapters you want to install from the list:

-
- The **Arbortext Adapter to Documentum** feature installs the Arbortext Adapter to Documentum product option. The adapter provides an interface between Arbortext Editor and the Documentum Server and is used to manage SGML content in Documentum. The instructions on configuring and using the Arbortext Adapter to Documentum appear in the Arbortext Content Management Guide. This product option does not require an additional license.

Note that this option is not available in the 64-bit version of the software.

- The **Arbortext Adapter to Documentum/WDK** feature installs the Arbortext Adapter to Documentum/WDK product option. The adapter provides the behavior of the Arbortext Adapter to Documentum/XML without requiring that the Documentum Desktop be installed on each workstation. The instructions on configuring and using the Arbortext Adapter to Documentum/WDK appear in the Arbortext Content Management Guide. This product option does not require an additional license.
- The **Arbortext Adapter to Documentum/XML** feature installs the Arbortext Adapter to Documentum/XML product option. The adapter is an interface between Arbortext Editor and the Documentum eContent Server. The instructions on configuring and using the Arbortext Adapter to Documentum/XML appear in the Arbortext Content Management Guide. This product option does not require an additional license.

Note that this option is not available in the 64-bit version of the software.

- The **Arbortext Adapter to IBM Document Manager** feature installs the Arbortext Adapter to IBM Document Manager product option. The Arbortext Adapter to IBM Document Manager provides an interface between Arbortext Editor and an IBM DB2 Document Manager server. The instructions on configuring and using the Arbortext Adapter to IBM Document Manager appear in the Arbortext Content Management Guide. This product option does not require an additional license.

Note that this option is not available in the 64-bit version of the software.

- The **Arbortext Adapter to Oracle CM SDK** feature installs the Arbortext Adapter to Oracle CM SDK product option. The Arbortext Adapter to Oracle CM SDK provides an interface between Arbortext Editor and an Oracle CM SDK server. The instructions on configuring and using the

Arbortext Adapter to Oracle CM SDK appear in the Arbortext Content Management Guide. This product option requires an additional license.

Clicking **Space** on the **Custom Setup** dialog box opens another dialog box showing the available disk space on your system.

Select the appropriate setup type for your installation, then click **Next** to continue the installation.

9. If you selected Arbortext Architect as a product to install, the `setup` program asks whether you would like to install Turbo XML. You can elect to install Turbo XML as an alternative to the text-based DTD Editor in Arbortext Architect.

If you elect to install Turbo XML, the `setup` program will start the separate installation program for Turbo XML after your Arbortext installation is complete. The `setup` program will configure Arbortext Architect to use Turbo XML when editing XML DTDs and schemas.

Indicate whether you want to install Turbo XML, then click **Next** to continue the installation.

10. The `setup` program asks whether you will be using the Arbortext Publishing Engine for document publishing. Check the box if you will be using Arbortext Publishing Engine. If so, you also have the option to enter the URL for your Arbortext PE server. It will have the following format:

```
http://servername:portnumber/e3/servlet/e3
```

Click **Next** to continue the installation.

11. The `setup` program indicates it is ready to install the program.

Click **Install** to continue the installation. The `setup` program displays the status of the installation.

12. The `setup` program indicates the installation is complete.

If you elected to install Arbortext Architect and Turbo XML, the `setup` program will start the Turbo XML installation program. You will need to reboot your system when the Turbo XML installation is complete.

Product Option Configuration on Windows

Product options are installed with the Arbortext Editor `setup` program and are stored in your Arbortext Editor installation directory. Available product options include:

-
- Arbortext Print Composer
 - Arbortext Web/Wireless Composer
 - Arbortext Import/Export
 - Turbo XML
 - Arbortext Adapter to Documentum/XML
 - Arbortext Adapter to Documentum/WDK
 - Arbortext Adapter to Documentum
 - Arbortext Adapter to IBM Document Manager
 - Arbortext Adapter to Oracle CM SDK

The availability of a given product option depends on the following:

- The product option must be installed. You can use the Arbortext `setup` program to install any of the product options at any time.
- The product option must be set on in the `Arbortext-path\lib\installprefs.acl` file. (*Arbortext-path* is where Arbortext Editor is installed.) The `setup` program automatically turns on the product options you've installed.
- The license for the product option must be available from the license manager.

Depending on the product options you installed and licensed, you may need to perform additional procedures to configure your product options.

Customizing the `installprefs.acl` File (Optional)

The `Arbortext-path\lib\installprefs.acl` file stores the “on” or “off” status of each of the Arbortext Editor product options. Each line in the `installprefs.acl` file is an Arbortext Command Language (ACL) `set` command for a specific product option. Each of these `set` commands is documented in the Arbortext Command Language Reference.

While the `setup` program creates the initial settings in this file, you may need to edit the `installprefs.acl` file for your site's specific needs. For example, if you have Arbortext Editor installed on a server for client access, all clients will use the `installprefs.acl` file from the server's installation directory. If you want certain clients to have specific product option settings, you will need to customize your `installprefs.acl` file.

Determine the features that should be available. Copy the default `Arbortext-path/lib/installprefs.acl` file, and edit the `set` feature commands accordingly.

Do this for each client-specific or group-specific set of features you want enabled. If you wish, you can rename the file (for example, `doc_installprefs.acl` or `sales_installprefs.acl`).

You can make custom `installprefs.acl` files automatically available by putting it in the user's `Arbortext-path\custom\lib` directory to load it automatically upon startup (avoiding the need to set an environment variable). Refer to *Description of the custom directory structure* in the Arbortext Help Center for more information.

You can set the `APTINSTALLPREFS` environment variable to the path and file name of the custom `installprefs.acl` file for each client or group. Navigate to the **Advanced** tab of the **System Properties** dialog box and choose the **Environment Variables** button.

Configuring Repository Adapters

If you installed a repository adapter, you will need to configure it before you use Arbortext Editor with your repository.

- For instructions on configuring the Arbortext Adapter to Documentum/XML, refer to the [Installing and configuring the Arbortext Adapter to Documentum/XML](#) in the Arbortext Content Management Guide.
- For instructions on configuring the Arbortext Adapter to Documentum/WDK, refer to the [Installing and configuring the Arbortext Adapter to Documentum/WDK](#) in the Arbortext Content Management Guide.
- For instructions on configuring the Arbortext Adapter to Documentum, refer to the [Arbortext Adapter to Documentum configuration overview](#) in the Arbortext Content Management Guide.
- For instructions on configuring the Arbortext Adapter to IBM Document Manager, refer to the [Configuring the adapter](#) topic in the Arbortext Adapter to IBM Document Manager section of the Arbortext Content Management Guide.
- For instructions on configuring the Arbortext Adapter to Oracle CM SDK, refer to the [Arbortext Adapter to Oracle CM SDK configuration overview](#). The installation instructions for the Arbortext Adapter to Oracle CM SDK servlet (which is installed on your CM SDK host) are located in the Arbortext Content Management Guide and on the Arbortext Editor distribution archive within the `/server/oracleifs/oracleifs.tar` and `\server\oracleifs\oracleifs.zip` archives.

7

License Information

Licensing Options for Arbortext Software	50
Licensing Prerequisites	52
Obtaining Licenses	54
Requesting Licenses	54
Receiving Your License Pack	56
Installing and Updating the License Server	56
PTC_D_LICENSE_FILE Environment Variable	57
Borrowing a License	58
Troubleshooting Licensing Problems	59

This chapter contains information and troubleshooting tips about licensing.

Licensing Options for Arbortext Software

Your Arbortext software needs either a node-locked FlexNet license or a floating FlexNet license to run. Arbortext software licenses are available online for customers covered by an active maintenance agreement. You must have a PTC online account and a Customer Number to get a license. If you do not already have one, you can establish a PTC online account at www.ptc.com/support/support.htm.

There are three basic types of licenses:

- A node-locked license for use on a single computer. This type of license is usually obtained by the end user.
- A floating license pack for a single computer that will be serving floating licenses to end users. This type of license is usually obtained by a system administrator.
- A floating license pack for a set of three servers (called a triad license server) that will be serving floating licenses to end users. This type of license is usually obtained by a system administrator.

Be sure to read [Requesting Licenses on page 54](#) for more information. Licensing information is stored on the user's system in an environment variable, regardless of the type of license. Refer to [PTC_D_LICENSE_FILE Environment Variable on page 57](#) for information.

It's possible that a system administrator will deploy the licensing information to your computer (which is stored in the `PTC_D_LICENSE_FILE` environment variable), and you may never be prompted for the information unless you encounter a problem. Refer to [Windows Installation Alternatives on page 33](#) for more information.

Node-Locked Licenses

A node-locked license is a local license file that allows Arbortext products to run on an authorized computer. The license file itself is stored on the computer. License files are generated from a Host ID code unique to each system. You can run an unlimited number of instances of Arbortext software on one authorized computer.

The PTC licensing web site uses your Arbortext software selection and version, customer number, and Host ID code to generate a node-locked license for the specified software.

Floating Licenses

Floating licenses are made available from a license server on a network to a set of users running the software. A license server allows multiple computers (license clients) on the network to run Arbortext software concurrently. The client computers running Arbortext software must specify the port and server name of the license server to obtain a floating license. If a license is available, the user is allowed to run the application.

The PTC licensing web site uses the Arbortext software selection and version, customer number, and Host ID code of the license server or servers to generate floating licenses for the specified software.

Your system administrator must install the FlexNet license management software and set up the necessary floating licenses before users can run their Arbortext products. See the instructions in [Installing and Updating the License Server on page 56](#).

A single-server configuration uses only one computer as the license server. Your site can implement server redundancy by using a triad license server. A triad server configuration uses three license servers. A triad server provides a fallback mechanism for Arbortext products to obtain licenses even if the main server goes down. Because a majority rule is in effect, at least two of the servers must be running for the triad server to function.

When you run Arbortext software with a floating license, you may need to specify the communications port number and license server name the first time you run the software. If prompted, you would enter the server information in the form `port@servername`; for example, `6789@aberdeen`.

You should verify the following with your network administrator:

- The FlexNet license server software has been installed and configured on the license server machine.
- The port number and server name of the license server on your network.

The FlexNet license management software and installer program are in the `flexlm` folder on the Arbortext software DVD or the license server download zip file available from the PTC Support site. Go to **Order or Download Software Updates** and find **PTC License Server: FLEXnet Publisher**. Choose the latest version of the download file for your system. The license server installation instructions are located at:

http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?&im_dbkey=90870&im_language=en

After the FlexNet software is installed, it must be configured to recognize the client computers as floating license clients. Consult the *FLEXnet Licensing End User Guide* in the `flexlm` directory for license management software setup and configuration instructions. You can also download this guide from the Reference Documents section on the PTC Support site at:

<http://www.ptc.com/support/>

Using Both License Types

Occasionally, someone may want to use both license types (either a node-locked license or a floating license) to enable Arbortext software to run. The application can search for both node-locked and floating licenses when attempting to obtain a license.

You must enter the information to locate both types of licenses, meaning the license file path for the locked license as well as the `port@servername` specification for the floating license server.

The values for both types of licenses are stored in the [PTC_D_LICENSE_FILE Environment Variable on page 57](#).

Licensing Prerequisites

To configure license(s) and obtain a license pack file, you need the following:

- Web access and a PTC customer account with an active maintenance agreement. You can register at <http://www.ptc.com/support>.
- Your customer login, password, and customer number for the Arbortext software you want to install.
- The Host ID code unique to the computer. You can get the Host ID in any of the following ways:
 - the first time you run the Arbortext software, if it can't obtain a license. A licensing dialog box will prompt for the information. Some users may not have to enter this information if their license administrator has already deployed license information to their computers.
 - by running `cpu_id.exe` from a Windows command prompt (available from the `flexlm` directory on the installation DVD or download zip or from the PTC support site).
 - by going to the following web page on the PTC support site for instructions:

http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?im_dbkey=90575&icg_dbkey=900

Node-Locked License Prerequisites

For each copy of Arbortext software you plan to install, you need to:

- Request a license on the PTC Support site at <http://www.ptc.com/support>. Have your customer login, password, customer number, and Host ID for the computer at hand.

If you are setting up a floating license server, be sure you have the Host ID and server name of the license server or servers (for a triad).

See [Requesting Licenses on page 54](#) for instructions.

- Receive the license pack file containing your configured license(s). The license pack file is a text file attached to an email from PTC License Management (LM@ptc.com). Save the attached license pack file to a folder on the computer where you will install your licenses.

See [Receiving Your License Pack on page 56](#) for instructions.

Floating License Prerequisites

The following prerequisites apply if you plan to install a license server to provide floating licenses:

- The floating license server must have the FlexNet license management software installed on it.

The FlexNet license management software and installer program are in the `flexlm` folder on the Arbortext software DVD or the license server download zip file available from the PTC Support site. Go to **Order or Download Software Updates** and find **PTC License Server: FLEXnet Publisher**. Choose the latest version of the download file for your system. The license server installation instructions are located at:

[http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?
&im_dbkey=90870&im_language=en](http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?&im_dbkey=90870&im_language=en)

Install this software on the license server. See the *FLEXnet Licensing End User Guide* for setup and configuration instructions. (Installing FlexNet license management software requires administrator privileges on the license server computer.)

- Your Arbortext software must have a working network connection to the license server and specify the port number and server name to request licenses.

Obtaining Licenses

You will need to obtain a new license for the Arbortext Editor 6.0 release. Beginning with Arbortext Editor 6.0, these licenses are backward compatible. This means that you must update your license each time you upgrade to a major Arbortext Editor F000 release (maintenance releases or datecode updates would not require a license update). Licenses requested for the next major release of Arbortext Editor after version 6.0 would still work for users running Arbortext Editor 6.0. For example, if the next major release is Arbortext Editor 6.1, a license issued for that version would be compatible with both 6.1 and 6.0.

Licenses issued for previous releases (such as 5.4) will not work with Arbortext Editor 6.0, but older versions of Arbortext Editor will continue to work with the license keys issued for them.

What You Will Need

When you obtain your license, you will need your PTC support site login information and customer number for the www.ptc.com/support/support.htm. You will also need the Host ID of the client (for a node-locked license) or server (for floating licenses) computer. Refer to [Requesting Licenses on page 54](#) for further information.

The PTC support web site might not offer license keys for all possible customer requests. Ask for assistance on the PTC Customer Support web site, if necessary, regarding any of the following:

- Modification of an existing license key to add new floating licenses to an existing server.
- Extension of a temporary license for evaluation.
- Generation of licenses for triad server configurations.

You can submit a request for help on the PTC Customer Support at www.ptc.com/support/support.htm by choosing **Log a New Call** under **Popular Tools** or **Customer Care Call Logger** under **Customer Care**. You can also contact PTC License management support by telephone. See www.ptc.com/olm/contacts for a list of contact numbers.

Requesting Licenses

Read the *License Management* chapter in your *PTC Customer Service Guide* before you start configuring Arbortext licenses. The general instructions in that chapter will prepare you for the licensing instructions that follow.

Also, be sure you've read [Licensing Options for Arbortext Software on page 50](#).

On the PTC Support web site, the licensing web tool steps you through the process of configuring your software to your hardware. You need a PTC.com web account login, your Customer Number, and your Host ID code unique to the computer. You can get the Host ID:

- the first time you run the Arbortext software, if it can't obtain a license. The **Licensing Error dialog box** will prompt for license source information and provide the Host ID for the system.
- by running `cpu_id.exe` from a Windows command prompt (available from the `flexlm` directory on the installation DVD or download zip or from the PTC support site).
- by going to the following web page on the PTC support site for instructions:
http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?im_dbkey=90575&icg_dbkey=900

It's possible that your system administrator has deployed the licensing information to your computer (which is stored in the `PTC_D_LICENSE_FILE` environment variable), and you may never be prompted for license information unless you encounter a problem. Refer to [Windows Installation Alternatives on page 33](#) for more information.

You will use the PTC **License Landing Page** to configure the Arbortext software licenses for your hardware.

1. Go to the PTC support page at <http://www.ptc.com/support>.
2. Choose **Arbortext**.
3. Choose **Licensing**.
4. Choose **Arbortext License Support** and log in to your PTC account when prompted. You will need your login name, password, and Customer Number.
5. Choose your **Product Family** from the list.
6. Choose the **Version** from the list. The **Hardware Selection** is then displayed.
7. Enter the **PTC Host Id** (available by following the directions at the beginning of this section). If your computer is already in the system, you can **Browse** for it.

Enter the name for your computer in the **Host/Triad Name**.

The **PTC Host Id** and **Host/Triad Name** identify one of the following:

- A single computer for a node-locked license.
- A single computer that will be serving floating licenses to end users.
- A set of three computers (called a triad license server) that will be serving floating licenses to end users. This type of licensing provides server redundancy.

Click **Continue**.

8. If the Host ID is not in the PTC licensing system, you will be asked to enter an installation address and contact that will be associated with the Host ID.
9. Confirm the combination of Arbortext software and your hardware for your license. Then click **Get License**. You will get a call number for confirmation of the request.

The license transaction is processed and the license file will be emailed to you, usually within 10 minutes.

Receiving Your License Pack

After you have finished [Requesting Licenses on page 54](#), a license pack file will be sent to you by email from LM@PTC.com. The attached license pack is a text file with a file name of the form `lm_XXXXXXXX_standard.txt`. The email message may contain licensing instructions for other PTC software products, depending on the content of the license pack file. Save the attached license pack file to a temporary location and note its location.

If you are using a locked license, you will be prompted to enter the license file location the first time you run Arbortext software. The information is stored in the [PTC_D_LICENSE_FILE Environment Variable on page 57](#). It's available from the **User variables** or **System variables** list on the **Environment** tab of your **System Properties** dialog box.

If you will be using a floating license but you are not configuring a license server, you will not be obtaining a license from PTC. You will instead enter the port number and server name the first time you run the software. See [Licensing Options for Arbortext Software on page 50](#) for information on license types.

Installing and Updating the License Server

If you are upgrading from a previous version of Arbortext software for the first time, and your installation uses floating licenses or a combination of node-locked and floating licenses, your license administrator will need to install the FlexNet License server. If a user attempts to use an upgraded version of the Arbortext software with an unsupported license server or an invalid license file, the **Licensing Error** dialog box displays the error and prompts for valid license information. If the FlexNet license server is already installed, it may not need to be upgraded when the Arbortext software is upgraded. Please refer to the Release Notes for your particular version for more information.

The FlexNet license server system is documented in the *FlexNet Licensing End User Guide*. This guide explains the basics of FlexNet floating (network) licensing, gives an overview of the FlexNet licensing components, and provides details on managing floating licenses for administrators. This guide is available from the `flexlm` directory of the Arbortext installation distribution (either from the DVD or zip download) and also from the Reference Documents web page of the PTC Support site at <http://www.ptc.com/support/>.

The FlexNet license management software and installer program are in the `flexlm` folder on the Arbortext software DVD or available in the license server download zip file from the PTC Support site. Go to **Order or Download Software Updates** and choose **PTC License Server: FLEXnet Publisher**. Choose the latest version of the download file for your system.

For instructions on installing the PTC FlexNet License Server as either a single server or a triad server, refer to the following Suggested Technique:

[http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?
&im_dbkey=90870&im_language=en](http://www.ptc.com/appserver/wcms/standards/freefull_cskdb.jsp?&im_dbkey=90870&im_language=en)

For more general information on floating licensing, see [Licensing Options for Arbortext Software](#) on page 50.

PTC_D_LICENSE_FILE Environment Variable

Be sure you have read [Licensing Options for Arbortext Software](#) on page 50 and [Requesting Licenses](#) on page 54.

Arbortext software looks for the `PTC_D_LICENSE_FILE` environment variable automatically when it starts. This variable setting provides the path to your node-locked license file or the `port@servername` specification where your software should retrieve a floating license. When you run Arbortext software for the first time, it checks for a valid license source in `PTC_D_LICENSE_FILE`. If it does not exist or has an incorrect value, you will need to specify it.

If you need to add or reset `PTC_D_LICENSE_FILE`, choose from the following:

- For a node-locked license file, set its value to the license file path.
- For a single floating license server, set its value to `port@servername`, for example, `6789@aberdeen`.
- For a triad server configuration, set its value to:

`port@servername1, port@servername2, port@servername3`

For example:

3456@able, 3456@baker, 3456@charlie

- For a combination of node-locked and floating licenses, you would set its value to both the license file path and the `port@servername`. Note that each type of license option is separated by a semicolon (;). For example:

```
C:\User Data\All Users\Application Data\Arbortext\  
lm_12345678_standard.txt;3456@able,3456@baker,3456@charlie
```

It's possible that your system administrator has deployed the licensing information to your computer (which is stored in the `PTC_D_LICENSE_FILE` environment variable), and you may never be prompted for the information unless you encounter a license problem. Refer to [Windows Installation Alternatives on page 33](#) and [Licensing Error dialog box](#) for more information.

Borrowing a License

If your site uses floating licenses, you may also be able to run Arbortext Editor while you are away from the network. Your FlexNet license server must have license borrowing configured and enabled. You can borrow a license for specific products and options to which you are entitled to have a license, and you can choose the time period up to the maximum allowed.

To borrow a license to work offline, choose **Tools ► Administrative Tools ► Borrow Licenses** to launch the [Borrow Licenses dialog box](#). From the list of **Available** licenses, you can highlight your choice and then set a duration period. Click the right arrow to move the license option to the **Borrowed** list. It appears as **(Pending)** until you click **Apply**, when the license request is sent to the license server.

If you expect to be able to borrow a license and encounter a problem, contact your license administrator to be sure:

- Your system is looking for the correct license server. Ask your system administrator for the correct value for the [PTC_D_LICENSE_FILE Environment Variable on page 57](#) on your system.
- License borrowing is enabled on the license server.
- The license server is configured to allow your client machine to obtain a borrowed license.

Troubleshooting Licensing Problems

Unable to Obtain a License

Arbortext users must have an active maintenance agreement, a PTC online account login and password, and a Host ID to get a license. Go to www.ptc.com/support/support.htm. to obtain a license. Refer to [Requesting Licenses on page 54](#) for more information.

Arbortext products display the **Licensing Error dialog box** when a license can't be found. There are a wide variety of reasons that your software can't obtain a license. For floating licenses, the more common error messages may report that the license server is down or that all licenses are in use. If so, you should wait a few minutes and try again. If the problem persists, contact your license administrator. For node-locked licenses, the error message may report that the path to the license file is not valid. If so, you will need to locate the license file and update the path.

Licensing information is stored in the [PTC_D_LICENSE_FILE Environment Variable on page 57](#). If it isn't defined correctly or isn't defined at all, the **Licensing Error dialog box** will prompt you to enter the correct licensing information.

Node-Locked License Problems

Check whether you have the correct path for your license file. Locate your license file and compare its location with the path specified in the **Licensing Error dialog box** or the `PTC_D_LICENSE_FILE` environment variable.

Floating License Problems

If you are unable to obtain a floating license, investigate the following:

- Check whether you have the correct license server port number and server name (or three consecutive servers if your site is using a triad license server). Ask your license administrator for the correct value for the license server and enter it in the **Licensing Error dialog box**.
- Contact your system administrator and ask if the license server is running.
- If your site is using a triad license server, and the first license server goes down, licenses might be unavailable for a few minutes until the backup servers start distributing licenses. Wait for a few minutes and restart your Arbortext software. If you receive the same message, contact your system administrator and ask if the triad server is running.

Unable to Renew a Floating License

If your Arbortext software session is inactive for a long period of time, the license manager (which serves floating licenses) may take back your license based on the FlexNet license server's `TIMEOUT (ALL)` configuration setting. If all available licenses are in use by other users when you resume your Arbortext software session, you will see an error message. The *FLEXnet Licensing End User Guide*, which explains the `TIMEOUT (ALL)` setting as well as other configuration settings, should be reviewed carefully by the license administrator.

This message might also appear if you are using a system in a remote location and connected to the license server over a VPN or dial-up connection. You may need to re-establish your connection before you can continue to use your Arbortext software. In such cases, license borrowing may be a more effective strategy. Refer to [Borrowing a License on page 58](#) for more information.

Index

A

- ACL scripts, editing, 29, 31
- Active Directory installation, 33, 36
- ActiveX controls
 - requirements for hosting, 10, 12
- ActiveX sample applications
 - requirements for running, 10, 12
- APP with Arbortext Styler or Arbortext PE
 - Perl, 11
- application files
 - overview of custom, 2930
- Arbortext Adapter to Documentum
 - installing, 40
- Arbortext Adapter to Documentum/XML
 - installing, 40
- Arbortext Adapter to Oracle CM SDK
 - servlet installation instructions, 47
- Arbortext Adapter to Oracle CM SDK
 - servlet installation instructions, 45
- Arbortext Editor
 - compact installation, 35
- Arbortext Editor
 - upgrading licenses, 54
- Arbortext Editor
 - upgrading software, 26
 - upgrading Windows versions, 26

- Arbortext Editor
 - upgrading software, 25
 - upgrading Windows versions, 25
- Arbortext Help Center
 - requirements, 11
- Arbortext Help Center
 - requirements, 10
- Arbortext Publishing Engine
 - publishing
 - setting up, 21

B

- borrowing a license, 58
- browser support
 - HTML publishing
 - Arbortext Editor 6.0, 10
 - web preview
 - Arbortext Editor 6.0, 10

C

- Chinese
 - product option support for, 10
- CJK languages
 - product option support for, 10
- commands
 - set writeentdecls, 2930
- compact installation
 - Arbortext Editor, 35
- custom applications
 - overview, 2930
- custom subdirectory, 2930
- customizations
 - disabling on test system, 25, 27

-
- testing, 29, 32
 - D**
 - disk space requirements
 - for Windows platforms, 20
 - Disk space requirements
 - for Windows platforms, 20
 - document types
 - recompiling, 29
 - downloaded file
 - installing from, 41
 - DVD
 - installing from, 41
 - E**
 - entity declarations, changing the default setting of, 2930
 - F**
 - FlexNet
 - license server, 56
 - floating licenses, 50
 - H**
 - hardware requirements
 - for Windows, 20
 - Host ID
 - for licensing, 50
 - HTML Help
 - system requirements, 2021
 - I**
 - installation
 - overview, 40
 - prerequisites, 40
 - installation information, 5
 - installing
 - compact installation, 35
 - license server, 56
 - Microsoft Windows 7, 34
 - Microsoft Windows Vista, 33
 - Windows Active Directory
 - installation, 33, 36
 - installing Arbortext Editor, 41
 - installprefs.acl file, 46
 - Internet Protocol Version 6 Support
 - Arbortext Editor, 11
 - Arbortext Editor, 10
 - PTC Server connection, 12
 - J**
 - Japanese
 - product option support for, 10
 - Java Virtual Machine
 - version, 1011
 - JAWS
 - requirements, 2021
 - K**
 - Korean
 - product option support for, 10
 - L**
 - languages
 - Chinese
 - product option support for, 10
 - Japanese
 - product option support for, 10
 - Korean
 - product option support for, 10
 - license
 - floating
 - prerequisites, 53
 - license server

- FlexNet, 56
- installing, 56
- licenses
 - borrowing, 58
 - floating, 50
 - inability to obtain, 59
 - node-locked, 50
 - prerequisites, 52
 - receiving, 56
 - requesting, 54
- licensing
 - setting
 - PTC_D_LICENSE_FILE, 57

M

- Microsoft Windows 7, 34
- Microsoft Windows Vista, 3334

N

- node-locked licenses, 50

P

- package customizations, 29, 31
- Perl
 - version required to support APP with Styler or PE, 11
- product installation information, 5
- product options
 - supported platforms and systems, 12
- product support
 - Arbortext Editor 6.0, 10
- PTC_D_LICENSE_FILE
 - setting for licensing, 57
- publishing using Arbortext Publishing Engine
 - setting up, 21

R

- recompiling document types, 29
- redundant license servers, 50
- requirements
 - software, 20

S

- server
 - single license, 50
 - triad license, 50
- set writeentdecls command, 2930
- single license server, 50
 - installing, 56
- stylesheets
 - update existing stylesheets, 23
- supported platforms and systems
 - Arbortext Editor 6.0, 10
- system requirements
 - for Windows, 20
 - fonts, 20
 - HTML Help, 20
 - JAWS, 20
 - System requirements for Windows, 2021
 - fonts, 20
 - HTML Help, 20
 - JAWS, 2021

T

- tag template customizations, 29, 31
- test system
 - disabling customizations, 25, 27
- triad license server, 50
 - installing, 56
- troubleshooting
 - licensing, 59

U

upgrading

- Arbortext product licenses, 54
- Arbortext products, 26
- Arbortext products, 25
- Arbortext software, 26
- Arbortext software, 25
- on Windows, 2526

W

web browser support, 10

- Arbortext Editor 6.0, 10
- Arbortext Editor 6.0, 10

Windows

- hardware requirements, 20

Windows Active Directory

- installation, 33, 36

working offline

- borrowing a license, 58