PTC®

Document - CS43569

Document Information

Type	Article
Date Created	07-Sep-2015 06:58:07 EDT
Date Last Updated	07-Sep-2015 06:58:08 EDT
Rating	1 Vote

Document Details

Title	Cannot insert *.BMP file in drawing using Pro/ENGINEER and Creo Elements/Pro
Description	- Cannot insert *.BMP file in drawing - Unable to embed bitmap image on a drawing - Unable to insert JPEG file in a drawing - Inserted image in drawings is displaying only image name. - Bitmap file is not displayed in the drawing
Applies To	- Pro/ENGINEER and Creo Elements/Pro Wildfire to Wildfire 5.0 - Creo Parametric Creo 1.0 to Creo 3.0
Cause	- The system's OLE settings are not configured correctly to perform this function. - The system's registry has been modified. - Installing Adobe Photoshop has been known to make undesirable modifications to the registry.
Resolution	- Resolution: - Adjust the system registry for .bmp files - PTC assumes no responsibility of the following steps - Registry modifications should be done by qualified system administrators - Remember to back up the registry before any modifications - If uncomfortable/unqualified, use workarounds below - Run **RegEdit** - Navigate to **HKEY_CLASSES_ROOT\.bmp** **RMB (Default) > Modify** - Change **Value Data** to **Paint.Picture** - Workaround 1: - Insert object into Microsoft Word document - Insert Microsoft Word document into Pro/ENGINEER **Insert** > **Object** > **From File** > **Browse** **Select** Word file > **Open** > **OK** - Workaround 2: **Open** bitmap file in Paint **Select All** > **Copy** - In Pro/ENGINEER, **Insert** > **Object** > **Create New** > **Paintbrush Picture/Bitmap File** **Paste** image into new window. **Save** and **Close** Paint

SPR Information

Related Documents

Type	Number	Status	Description

Social Media
Directory