

PTC[®]

Arbortext[®] IsoView[®]
Installation Guide

Arbortext IsoView 7.3

May 2012

Copyright © 2012 Parametric Technology Corporation and/or Its Subsidiary Companies. All Rights Reserved.

User and training guides and related documentation from Parametric Technology Corporation and its subsidiary companies (collectively "PTC") are subject to the copyright laws of the United States and other countries and are provided under a license agreement that restricts copying, disclosure, and use of such documentation. PTC hereby grants to the licensed software user the right to make copies in printed form of this documentation if provided on software media, but only for internal/personal use and in accordance with the license agreement under which the applicable software is licensed. Any copy made shall include the PTC copyright notice and any other proprietary notice provided by PTC. Training materials may not be copied without the express written consent of PTC. This documentation may not be disclosed, transferred, modified, or reduced to any form, including electronic media, or transmitted or made publicly available by any means without the prior written consent of PTC and no authorization is granted to make copies for such purposes.

Information described herein is furnished for general information only, is subject to change without notice, and should not be construed as a warranty or commitment by PTC. PTC assumes no responsibility or liability for any errors or inaccuracies that may appear in this document.

The software described in this document is provided under written license agreement, contains valuable trade secrets and proprietary information, and is protected by the copyright laws of the United States and other countries. It may not be copied or distributed in any form or medium, disclosed to third parties, or used in any manner not provided for in the software licenses agreement except with written prior approval from PTC.

UNAUTHORIZED USE OF SOFTWARE OR ITS DOCUMENTATION CAN RESULT IN CIVIL DAMAGES AND CRIMINAL PROSECUTION. PTC regards software piracy as the crime it is, and we view offenders accordingly. We do not tolerate the piracy of PTC software products, and we pursue (both civilly and criminally) those who do so using all legal means available, including public and private surveillance resources. As part of these efforts, PTC uses data monitoring and scouring technologies to obtain and transmit data on users of illegal copies of our software. This data collection is not performed on users of legally licensed software from PTC and its authorized distributors. If you are using an illegal copy of our software and do not consent to the collection and transmission of such data (including to the United States), cease using the illegal version, and contact PTC to obtain a legally licensed copy.

Important Copyright, Trademark, Patent, and Licensing Information: See the About Box, or copyright notice, of your PTC software.

UNITED STATES GOVERNMENT RESTRICTED RIGHTS LEGEND

This document and the software described herein are Commercial Computer Documentation and Software, pursuant to FAR 12.212(a)-(b) (OCT'95) or DFARS 227.7202-1(a) and 227.7202-3(a) (JUN'95), and are provided to the US Government under a limited commercial license only. For procurements predating the above clauses, use, duplication, or disclosure by the Government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software Clause at DFARS 252.227-7013 (OCT'88) or Commercial Computer Software-Restricted Rights at FAR 52.227-19(c)(1)-(2) (JUN'87), as applicable. 01012012

Parametric Technology Corporation, 140 Kendrick Street, Needham, MA 02494 USA

Contents

About This Guide.....	5
Installation Requirements.....	11
System Requirements.....	12
Supported Operating Systems and Web Browser	12
Installing Arbortext IsoView	13
Installer Folders	14
Running the Installer	15
Removing Arbortext IsoView.....	17



About This Guide

This guide provides installation instructions for the Arbortext IsoView 7.2 Distribution Kit software. It also describes how to remove (uninstall) Arbortext IsoView software.

These instructions apply to both new installations and systems with Arbortext IsoView 7.0 M010 or later installed.

Note

Arbortext IsoView 7.0 M010 or later software is automatically updated and replaced when you install Arbortext IsoView 7.2. However, Arbortext IsoView 7.0 F000 or earlier is not. If you do not uninstall Arbortext IsoView 7.0 F000 or earlier before you install Arbortext IsoView 7.2, the 7.0 F000 or earlier software remains on disk but will not run after you install 7.2. (See [Removing Arbortext IsoView on page 17.](#))

Prerequisites

Before you install Arbortext IsoView 7.2, verify that your computer meets all the requirements in [Installation Requirements on page 11](#). You will also need a working knowledge of Microsoft Windows XP, Windows Vista, or Windows 7.

Guide Organization

This *Arbortext IsoView Installation Guide* has two sections:

- [Installation Requirements on page 11](#), specifies the minimum and recommended hardware and software configurations required to run Arbortext IsoView 7.2.
- [Installing Arbortext IsoView on page 13](#) describes how to install and remove the Arbortext IsoView software.

Related Documentation

For more information on Arbortext IsoView and Arbortext IsoDraw products, refer to the following documentation found in the Arbortext IsoDraw Help Center. The Help Center includes both HTML and PDF versions of the documentation. If you have Arbortext IsoDraw 7.2 or later installed, choose **Help ► Help Center** to access it. You can also access the Arbortext IsoDraw Help Center through the Help Center link available from the main Support section on <http://www.ptc.com>.

For Arbortext IsoView information:

Documentation	Description
<i>Arbortext IsoView Release Notes</i>	Information about new, changed, and deleted features in this Arbortext IsoView release.
<i>Arbortext IsoView Installation Guide</i>	(This guide.) Installation and licensing information for Arbortext IsoView.
<i>Arbortext IsoView User's Reference</i>	Instructions for using the tools and functions in Arbortext IsoView, and for setting preferences.
<i>Arbortext IsoView Programmer's Reference</i>	Reference for writing API scripts that customize and extend the Arbortext IsoView ActiveX control.

For Arbortext IsoDraw information:

Documentation	Description
<i>Arbortext IsoDraw Release Notes</i>	Information about new, changed, and deleted features in this Arbortext IsoDraw release.
<i>Installing Arbortext IsoDraw</i>	Installation and licensing information for Arbortext IsoDraw.
<i>Drawing Basics Tutorial</i>	Hands-on examples for learning Arbortext IsoDraw basic functions.
<i>3D Mode Tutorial</i>	Hands-on examples for learning 3D CAD data editing functions using

Documentation	Description
	Arbortext IsoDraw.
<i>Arbortext IsoDraw User's Reference</i>	Comprehensive guide to using the tools and functions in Arbortext IsoDraw products.
<i>Arbortext IsoDraw Macro Language Reference</i>	Reference for writing macros that you can run in Arbortext IsoDraw.
<i>Arbortext IsoDraw Data Exchange Reference</i>	Instructions for importing and exporting graphics data in various formats to and from Arbortext IsoDraw.

Technical Support

Contact PTC Technical Support via the PTC Web site, phone, fax, or e-mail if you encounter problems using your product or the product documentation.

For complete details, refer to *Contacting Technical Support* in the PTC Customer Service Guide. This guide can be found under the CONTACTING TECHNICAL SUPPORT section of the PTC Web site at:

<http://www.ptc.com/support/>

The PTC Web site also provides a search facility for technical documentation of particular interest. To access this search facility, use the URL above and select Search the Knowledge Base.

You must have a Service Contract Number (SCN) before you can receive technical support. If you do not have an SCN, contact PTC Maintenance Department using the instructions found in your *PTC Customer Service Guide* under *Contacting Your Maintenance Support Representative*.

Documentation for PTC Products

You can access PTC product documentation using the following resources:

- Online Help

Click **Help** from the user interface for online help available for the product.

- Reference Documents

Individual product manuals are available from the Reference Documents link of the PTC Web site at the following URL:

<http://www.ptc.com/support/>

- Help Center

A searchable product documentation knowledge base is available from the Help Center link of the PTC Web site at the following URL:

<http://www.ptc.com/support/>

You must have a Service Contract Number (SCN) before you can access the Reference Documents or Help Center Web site. If you do not have an SCN, contact PTC Maintenance Department using the instructions found in your PTC Customer Service Guide under Contacting Your Maintenance Support Representative.

Global Services

PTC Global Services delivers the highest quality, most efficient and most comprehensive deployments of the PTC Product Development System including Pro/ENGINEER, Windchill, Arbortext and Mathcad. PTC's Implementation and Expansion solutions integrate the process consulting, technology implementation, education and value management activities customers need to be successful. Customers are led through Solution Design, Solution Development and Solution Deployment phases with the continuous driving objective of maximizing value from their investment.

Contact your PTC sales representative for more information on Global Services.

Comments

PTC welcomes your suggestions and comments on our documentation. You can submit your feedback to the following email address:

arbortext-documentation@ptc.com

Please include the following information in your email:

- Name
- Company
- Product
- Product Version
- Document or Online Help Topic Title
- Level of Expertise in the Product (Beginning, Intermediate, Advanced)
- Comments (including page numbers where applicable)

Documentation Conventions

This guide uses the following notational conventions:

- **Bold text** represents exact text that appears in the program's user interface. This includes items such as button text, menu selections, and dialog box elements. For example,
Click **OK** to begin the operation.
- A right arrow represents successive menu selections. For example,
Choose **File** ► **Print** to print the document.
- Monospaced text represents code, command names, file paths, or other text that you would type exactly as described. For example,
At the command line, type `version` to display version information.
- *Italicized monospaced text* represents variable text that you would type. For example,
`installation-dir\custom\scripts\`
- Italicized text represents a reference to other published material. For example,
If you are new to the product, refer to the Getting Started Guide for basic interface information.

1

Installation Requirements

System Requirements.....	12
Supported Operating Systems and Web Browser.....	12

System Requirements

Requirement	Platform		Minimum	Recommended
	32 bit	64 bit		
PC processor	●		1 GHz x86	≥ 2 GHz x86
RAM			1 GB	≥ 1 GB
PC processor		●	1 GHz x64	≥ 3 GHz x64
RAM			1 GB	≥ 4 GB
Graphics card	●	●	OpenGL support; 16-bit color palette; 800 × 600 screen resolution	OpenGL support; 32-bit color palette; 1280 × 1024 screen resolution
Free space on hard disk	●	●	50 MB	50 MB
Keyboard	●	●	With function keys	Same
Mouse	●	●	2-button	Same
Printer	●	●	When using a PostScript printer, the printer driver should support PostScript for faster printing.	Same

Supported Operating Systems and Web Browser

Windows XP (32-bit) with Service Pack 3 or above
Windows XP Professional Edition (64-bit) with Service Pack 2
Windows 7 (32-bit)
Windows 7 (64-bit)
Microsoft Internet Explorer 7.0 or later (32-bit only) with ActiveX enabled and Protected Mode disabled when running in Windows Vista or Window 7

2

Installing Arbortext IsoView


Installer Folders.....	14
Running the Installer.....	15
Removing Arbortext IsoView.....	17

To install all required Arbortext IsoView Distribution Kit software, you must run the installer program, `IsoViewX72.exe`. This program is in the `\IsoView\EXE` folder on your Arbortext IsoView CD or in the Arbortext IsoView download ZIP file. (See [Running the Installer on page 15.](#))

You can also use the installer program to remove (uninstall) your existing Arbortext IsoView software installation. (See [Removing Arbortext IsoView on page 17.](#))

Installer Folders

Open your Arbortext IsoView 7.2 CD or Arbortext IsoView 7.2 download Zip file temporary folder in Windows Explorer and browse the installer folders. Each folder's contents are described below.



Documentation Folder

The `Documentation` folder contains the documentation you can read before you install Arbortext IsoView 7.2 software.

- (This guide.) *Arbortext IsoView Installation Guide* (`isov-inst.pdf`)
- *Arbortext IsoView Release Notes* (`isov-relnotes.pdf`)
- *Arbortext IsoView User's Reference* (`isov-uref.pdf`)
- *Arbortext IsoView Programmer's Reference* (`isov-pref.pdf`)

Note

If you have Arbortext IsoDraw 7.2 software installed, you can also access these Arbortext IsoView 7.2 documents by choosing **Help ► Help Center** in Arbortext IsoDraw 7.2.

IsoView Folder

The `IsoView` folder contains three subfolders. Each subfolder contains the Arbortext IsoView 7.2 Distribution Kit installer program file in a different format.

- `\IsoView\CAB` contains `IsoViewX72.cab` in Microsoft native compressed archive format.
- `\IsoView\EXE` contains `IsoViewX72.exe` in executable format.
- `\IsoView\MSI` contains `IsoViewX72.msi` in Windows Installer format.

The instructions in this guide assume you will run the `IsoViewX72.exe` installer in `\IsoView\EXE`. However, all three installers launch the same Installation Wizard, so the instructions are the same regardless of which installer you run.

Running the Installer


Run `IsoViewX72.exe` in the `\IsoView\EXE` folder to start the Arbortext IsoView 7.2 installer program. The **Arbortext IsoView 7.2 - InstallShield Wizard** dialog box appears.



Click **Next** to continue installation.

Arbortext IsoView License Agreement

Review the license agreement and then select the option to accept it in the **License Agreement** dialog box below. Click **Next**.



The **Next** button is unavailable until you select the option to accept the license agreement. If you do not accept the license agreement, you cannot continue installation. If you click **Cancel**, you will terminate the Arbortext IsoView installation.

Completing Arbortext IsoView Installation

1. Accept the license agreement and click **Next**. The **Destination Folder** page appears.
2. Click **Next** to if you want to install the Arbortext IsoView 7.2 software in the default destination folder:

C:\Program Files\PTC\Arbortext IsoView 7.2\

If you want to install the software in a different destination folder:

- a. Click **Change** to open the **Choose Folder** dialog box.
- b. Choose a different destination folder and then click **OK**.
- c. Click **Next** to continue.

3. In the **Ready to Install the Program** page, click **Install**. While the Arbortext IsoView 7.2 software is being configured and installed, the **Setup Status** page displays a progress bar.
4. When installation is complete, the **InstallShield Wizard Completed** page appears. Arbortext IsoView 7.2 is now installed on your computer. Click **Finish**.



Removing Arbortext IsoView

You can remove (uninstall) Arbortext IsoView software from your computer in either of the following ways:

- Run the installation program, `IsoViewX72.exe`. If the program detects Arbortext IsoView software on your computer, you will have the option to uninstall it.
- Use the Windows Control Panel. Select Arbortext IsoView from the list of installed programs, and then select the command or option to change/remove it. (This removal method varies depending on your Windows operating system. See Windows Help for instructions.)

After performing either action above, follow the instructions below to remove Arbortext IsoView software.

Note

Arbortext IsoView 7.0 M010 or later software is automatically updated and replaced when you install Arbortext IsoView 7.2. However, Arbortext IsoView 7.0 F000 or earlier is not. If you do not uninstall Arbortext IsoView 7.0 F000 or earlier before you install Arbortext IsoView 7.2, the 7.0 F000 or earlier software remains on disk but will not run after you install 7.2.

1. When you see the **Do you want to completely remove this application...** message box, click **Yes**.

Removal begins. The **Setup Status** page displays a progress bar along with the message **The InstallShield Wizard is removing** Arbortext IsoView.

2. When removal is complete, the **Uninstall Complete** page appears. Arbortext IsoView software is now removed from your computer.
3. Click **Finish** to exit the installation program.
4. If you want to (re)install Arbortext IsoView 7.2, run the installation program, `IsoViewX72.exe`, again.

